

Description	3
High-Level Administration REST API	3
Plain Production REST API	3
Extended Production REST API	3
Consortium Signature Cloud API	3
Business Activity Monitoring API	3
Extended Production Com API	3
Installation	4
Configuration	5
Additional information	8

## **Description**

**P5RAPI** is a **production REST service**. P5RAPI service enables you to exchange data with **Sage XRT Business Exchange** through the REST APIs described in the following sections.

### **High-Level Administration REST API**

This type of REST APIs enables the management of the platform for **SFB** profile: **SFB** provisioning, company publication, etc.

#### Plain Production REST API

This type of REST APIs monitors the bank flows life cycle, for example, when a file is added into the Signature Station, when files are received or sent, statuses, etc.

#### Extended Production REST API

This type of APIs enables access to advanced production APIs, for example to obtain the list of files to sign, or to send, etc.

### **Consortium Signature Cloud API**

This type of APIs enables the management of certificates in the cloud in compliance with **CSC** standard, for example to get the certificates list, to calculate signatures or to authenticate signatories.

## **Business Activity Monitoring API**

This type of APIs enables the retrieval of info. (statistics of consumption or use, technical data, etc.) on the product and its environment, for example to get the list of the available statistical models, to start an analysis, etc.


These APIs also launch your maintenance plans and get results from them.

#### **Extended Production Com API**

This type of APIs enables access to communication APIs, for example to initialize, renew and revoke bank contracts or to edit initialization letters.


### Installation

**P5RAPI production REST service** is included in the installation package of **Sage XRT Business Exchange**.



P5RAPI must be started with a service account.

You can view all the APIs that are already in this version.




Access to API is restricted to the following rights in Sage XRT Common Services.




# **Configuration**

You need to set up the service from the **System Administration** interface.



A setup wizard helps you go through the process.



## Configuration

Key	Comments	
General Settings		
UseSecureChannel	https or http (by default https)	
	Server Name, empty by default (Station Name)	
AdditionnalPath	Access Path to REST API, by default srp	
Adress Public	Public address of the server	
Cache Session expiration	General Cache Timeout, 10 minutes by default	
NotificationAlias	Alias for the notification, used for signature	
NotificationEntity	Entity Alias for the notification, used for signature	
	REST API access port, 443 by default	
LogFile	By default path and log of the service, deactivated if no value is specified	
ActiveDocumentation	To select to enable the swagger documentation	
DefautAuthScheme	Authentication Method	
OAuth Authentication Parameters		
OAuthDecryption	Self-generated decryption key, default value: Auto	
OAuthValidationAlgorithm	Self-generated validation algorithm, HMACSHA256 by default	
OAuthValidationKey	Self-generated validation key, AutoGenerate, IsolateApps	
OAuthDecryptionKey	Self-generated decryption key, AutoGenerate, IsolateApps	

## Configuration


Key	Comments	
OAuthAccessTokenExpire	Access Token Lifetime in minutes indicates 30 by default	
OAuthModeSupport	Value: TokenEndpointServer When TokenEndPoint is specified, P5RAPI becomes an identity and access token server. To recover a valid Oauth2 token, P5RAPI + /token address must be called. If not specified, P5RAPI is just a resources server.	
JWT Authentication Parameters		
Realm	JWT domain	
Issuer	Issuer value	
Audience	Audience value	
Secret	Secret value	
Certificate	Certificate Name	
CertificateFindType	Search method for certificate, by default DN of certificate object name. Value: FindBySubjectDistinguishedName	
SAML Authentication Parameters		
Audience	Audience value	
ThumbPrint	Issuer Thumb Print value	
Issuer	Issuer Name value	

### **Additional information**

The service can be used in Debug Mode through:

#### \\Program Files\Sage\Sage XRT Business Exchange\p5rapi.exe NoService

The log file can be accessed in the location specified during the services setup. The value **= LogFile** must be specified.



The events occurring on P5RAPI production REST service are registered in the monitor.

